


HOW TO SET UP MUSTANG MAIL!

How to set up for IOS devices

1. Open Settings
2. Select "Mail, Contacts, Calendars"
3. Select "Add Account"
4. Select "Other" (the option at the bottom of the list)
5. Select "Add Mail Account"
6. Enter your info here and click "Next"
7. Leave the selection on IMAP add the following information
8. Hostname for incoming and outgoing mail server is mail.usw.edu
9. Username should be aXXXXX
10. Password should be Mustang#### or whatever you may have changed it to
11. Select Next and the device will check the authentication settings
12. Select next again
13. Select Save

Assuming username, hostnames and password are entered correctly in both servers you should be ready to begin receiving email on your iOS device.




How to set up for Android devices

1. Open Settings
2. Under Accounts (Accounts & Sync) section, Select -"+ Add account"
For some devices this option will be in the -General or Account tab
3. Select IMAP (or Personal IMAP or IMAP4)
4. Fill out the "Email" and "Password" and click "Next"
5. For the Incoming Server settings, Username should be aXXXXX
6. The server is mail.usw.edu
7. Port 993
8. Security Type is SSL (SSL/TLS option in some devices)
9. Select "Next" if required
10. For Outgoing Server settings, "SMTP Server" is mail.usw.edu
11. Port 587
12. Security Type should be TLS (or STARTTLS for some devices)
13. If Username is require make sure is aXXXXX
14. Select "Next" if required
15. Select you preferred "Sync frequency"
16. Select "Next" again

HOW TO SET UP MUSTANG MAIL!

How to connect an HP stream to student email using the Microsoft Mail App for Windows 8.1

1. Open the mail app
2. Move mouse cursor over top right corner of screen to open the charms menu
3. Select the Settings Option
4. Select the Accounts option
5. Select “Add and account”
6. Select Other account
7. Click the radio button for IMAP and click “Connect”
8. Enter email address and password
9. Click “show more details”
10. Enter mail.usw.edu as outgoing and incoming mail server
11. Enter username
12. Leave all boxes checked and make sure that the port listed for incoming mail server is 993 and the port for outgoing mail server is 587.
13. Click Connect



Notes:

- You must be logged on onto Mustang Wireless to be able to connect to Mustang Mail.
- If you are still having trouble connecting your devices, please visit the Technology department located in the Mabee Center of Teaching and Learning, or contact technology services at (575) 492-2182.